Installation Steps

Flow

[1.Server Settings] Setting up the server to run EC-CUBE.

[2.Files/Folders] Placing EC-CUBE's files on the server.

[3. Initial Settings] Using your browser to access the EC-CUBE installation screen. Follow the steps shown on the screen to set up.

System Requirements

・WEB server… Apache 2.0.x.2.2x or greater, IIS7.0 or greater.

・PHP … 5.1.6 or greater.

・Database … PostgresSQL 8.1.4.9.x or greater, mySQL5.0.x or greater

PHP's Library Requirements

Required … pgsql, mysql, gd, freetype2, mbstring, zlib, spl (only with PHP 5.3.0 or older)

Recommended … JSON, xml, OpenSSl, cURL, hash, mhash, mcrypt

3 Steps Details

1. Server settings

Follow the below steps in order to set up the server.

Important

When using a virtual host, change "httpd.conf" to:

```
NameVirtualHost xxx.xxx.xxx.xxx:80
<VirtualHost xxx.xxx.xxx.xxx>
    ServerName site.example.net
    DocumentRoot /usr/local/eccube-2.12.0/html
    DirectoryIndex index.html index.php
</VirtualHost>
```

2. Files/Folders

Authorization Settings…Upload the files/folders (shown below) and change the directory's "permissions".

・html/ … permission：777

・data/cache … permission：777

・data/class … permission：777

・data/config … permission：777

・data/downloads … permission：777

・data/logs … permission：777

・data/Smarty … permission：777

・data/upload … permission：777

3. Initial Settings

Installation Steps.

① Access EC-CUBES's unzipped location
(for example in this case, http://site.example.net/install/) and click "Next"



② Verification of Access Authorization

③ Required files will be copied to EC site systems.

After confirming all of the information, click “Next”.

④ Enter information shown below and click “Next”.

EC Site Settings
・Shop name（Required） … Name of shop
・E-mail address（Required） … Address for orders (Ex: test@example.net)
・Log in ID（Required） … Log in ID for administrator screen
・Password（Required） … Password for administrator screen

Admin Settings
・Directory … Directory name for admin settings
・SSL Limit … Admin access’s SSL connection limit
・IP Limit … Admin access’s IP connection limit

WEB Server Settings
・URL（Normal）（Required） … URL of shop (Ex: http://site.example.net)
・URL（Secured）（Required） … Encrypted URL for personal information sent via forms (Ex: https://site.example.net)
・General Domain … With normal and SSL’s URL, a sub domain can be used with different forms

⑤ Enter database information and click “Next”.

・Types of DB（Required） … Select the type of DB (Database) to use
・DB Server（Required） … Input the DB server’s IP address
・Port … Input DB server’s port number
・DB Name（Required） … Input the name of DB to use
・DB User（Required） … Input the user name of DB
・DB Password（Required） … Input DB password

⑥ Click on “Next” to start the initialization of the database.

⑦ The status of the database will show up on the screen. Click “Next”.



⑧ Installation completed.

Important

Please delete the “index.php” in the folder “ *html/install”. This folder includes the configuration data during the installation process.

EC-CUBE Installation Steps.

EC-CUBE has established a community where users can solve problems by posting and sharing information with each other.

Please post your issues at the address below. We encourage feedback because it will better our system!

http://en.ec-cube.net/forum